Segment Installation Procedures Netscape SuiteSpot Servers (SSpot) Version 1.0.0.0 (HP-UX 10.20)

September 12, 1997

DII.30.FNL.HP-UX10.20.SSPOT.IP

Table of Contents

Prefac	ce	11
1. In	stallation Procedures	1
1.1	Scope	
1.1.1	Identification	
1.1.2	System Overview	
	·	
2. R	eferenced Documents	3
3. Sy	ystem Environment	5
3.1	System Requirements	5
3.1.1	Hardware Requirements	5
3.1.2	Operating System Requirements	5
3.1.3	Kernel Requirements	
3.2	System and Site Preparations	
3.2.1	System Configuration	
3.2.2	Operation System Preparation	
3.2.3	Tape/Disk Preparation	5
4. In	stallation Instructions	7
4.1	Media Booting Procedures	7
4.2	Installation Procedures for the SuiteSpot Segment	
4.2.1	De-Installation Instructions	7
4.3	Installation of Upgrades	
4.4	Installation Verification	7
4.5	Initializing the Software	
4.6	List of Changes and Enhancements	
4.7	Important Considerations	
5 N.	otas	۵

Preface

The following conventions are used in this document:

Bold Used for information that is typed, pressed, or selected in executables

and instructions. For example, select connect to host.

Italics Used for file names, directories, scripts, commands, user IDs, document

names, and Bibliography references; and any unusual computerese the

first time it is used in text.

<u>Underline</u> Used for emphasis.

Arrows <> Used to identify keys on the keyboard. For example <Return>.

"Quotation Marks" Used to identify informal, computer-generated queries and reports, or

coined names; and to clarify a term when it appears for the first time.

For example "Data-Generation Report."

Courier Font Used to denote anything as it appears on the screen or command lines.

For example tar xvf dev/rmt/3mm.

Capitalization Used to identify keys, screen icons, screen buttons, field, and menu

names.

1. Installation Procedures

1.1 Scope

These Installation Procedures (IP) provide a quick reference for installing the Netscape SuiteSpot Server (SSpot) segment for the Defense Information Infrastructure (DII) on Hewlett-Packard (HP)-based machines.

1.1.1 Identification

This section contains identification information for the SuiteSpot segment:

Segment Name: Netscape SuiteSpot Servers

Segment Type: COTS:COE CHILD

Prefix: SSpot

Home Directory: /h/COTS/SuiteSpot

Required License: None Version Number: 1.0.0.0

Platform: HP (UNIX) Workstation/HP-UX 10.20

1.1.2 System Overview

This section contains system overview information for the SuiteSpot segment:

Purpose: SSpot is a place holder segment for the Netscape SuiteSpot server

applications. The segment provides a directory for the segments which

comprise Netscape's SuiteSpot to install themselves.

Usage: This segment is required by all of the SuiteSpot server segments.

References: None.

2	D	ofor	on	hoo	Da	 men	40
Z.	ĸ	erer	ен	cea	170	пеп	18

3. System Environment

3.1 System Requirements

3.1.1 Hardware Requirements

The following HP hardware is necessary to install the SSpot segment:

- C HP-UX 10.20
- C 15500 KB of disk space
- C No memory space is required

3.1.2 Operating System Requirements

The HP operating system must be at least HP-UX 10.20 to install the SSpot segment.

3.1.3 Kernel Requirements

The following DII COE Kernel is required to install the SSpot segment:

DII COE Kernel V3.2 for HP-UX 10.20

3.2 System and Site Preparations

3.2.1 System Configuration

Enter the Netscape SuiteSpot Server segment into the COE Component Table (/h/COE/data/Comp_Table).

3.2.2 Operation System Preparation

None.

3.2.3 Tape/Disk Preparation

4. Installation Instructions

4.1 Media Booting Procedures

None.

4.2 Installation Procedures for the SuiteSpot Segment

This section describes the procedures required to install the SSpot segment on DII HP machines.

Step 1: Select the **Netscape SuiteSpot Servers** label from the COEInstaller's Select Software to Install window.

Step 2: Click the **Install** button.

4.2.1 De-Installation Instructions

To de-install the SSpot segment, one must first have removed any Netscape server instantiations from the platform via Netscape's Admin Server. To use the Admin Server, run a web browser and connect to http://machine_name:5350/ (where machine_name is the name of the machine upon which the SuiteSpot Servers is installed) and/or http://machine_name:5351/ and follow the on-line instructions for removing a server. Once all SuiteSpot Servers instantiations are removed, then the segment will de-install via the COEInstaller.

4.3 Installation of Upgrades

None.

4.4 Installation Verification

To verify that this software has been installed, execute the following commands:

```
cd /h/COTS/SuiteSpot
ls
```

If the directories *ns-home-2*, *ns-home-3*, and *SegDescrip* are present, then the segment installed correctly.

4.5 Initializing the Software

Not required.

4.6 List of Changes and Enhancements

Not applicable.

4.7 Important Considerations

5	Notes
⋾.	NOIRS